

Forum:[Hack Forums](#)

Thread: [\[VPN\] How to get a free vpn *No Downloads*\[VPN\] Windows 7/xp](#)

xxxLogins - January 4, 2012, 7:26 am

xxxLogins Here Showing you How To Get VPNReactor On Your PC ?

to see if your vpn is connected, go to www.ipchicken.com without being connected to your vpn and copy the ip, paste it somewhere or memorize it, then connect to your vpn and go back to ipchicken.cm and see if its changed.

Windows 7 ONLY

1. Click "Start" menu
2. Select "Computer"
3. Right click "Network" on the left hand side and Select 'Properties'
4. Click "Setup a new connection or network"
5. Select "Connect to a workplace" and click 'Next'
6. Click "Use my Internet connection (VPN)"
7. Type in the Internet address: vpn.vpnreactor.com and Destination name: VPNReactor
8. Go to vpnreactor.com and sign up "top right"
9. Enter your VPNReactor username and password in 'Username' and 'Password' field and click "Connect"

Now you are connected to VPNReactor.

Once connected go to vpnreactor.com to verify that your connection is now secure.

To disconnect the VPN click the wifi bars or the computer on your taskbar, look for "Vpn Reactor" double click and click disconnect (same for connecting)

Windows XP ONLY

1. Choose Start > Connect To > Show All Connections
2. click on "Create a new connection" on the left hand side

3. Choose "Connect to the network at my workplace" and click "Next".
4. Choose "Virtual Private Network connection" and click "Next"
5. Enter a name for the VPN connection (e.g. "VPNReactor") and click "Next".
6. If you don't need to dial up to the Internet before you can connect to VPNReactor, Choose "Do not dial the initial connection".
7. Enter "vpn.vpnreactor.com" as the VPN server host name and click "Next".
8. Check "Add a shortcut to this connection to my desktop" if desired, then click "Finish".
9. You should now disable "File and Printer Sharing" as it can pose as a security issue. Open the newly created VPNReactor connection and click "Properties". Click on the "Networking" tab, uncheck the "File and Printer Sharing for Microsoft Networks" and Click Ok.
10. To use VPNReactor, Enter your VPNReactor user name and password and click "Connect"

If your having any problems with this, contact me on aim or skype

Aim : DDoSFluxx

Skype : og.pastorship

thanks for reading my post (:

- xxxLogins

bernardbear - January 5, 2012, 10:54 am

is there any vpn except vpn.vpnreactor.com ?

The Online Boss - February 9, 2012, 4:54 am

I dislike this vpnreactor, you can only be on it for 30 minutes then it times you out for 30 minutes 30 on 30 off pretty bad=/

conair - April 7, 2012, 8:20 am

Thanks Man, Works like a charm! ?