

Forum:[Hack Forums](#)

Thread: [Fatal error: Allowed memory size of 33554432 bytes exhausted](#)

Sahaj - July 13, 2015, 2:59 am

Hi, good morning/afternoon/evening. :)

I recently bought pro hosting from [here](#).

I installed Wordpress today and it was working great. But when I installed a custom theme, I got this error message :

Quote:Fatal error: Allowed memory size of 33554432 bytes exhausted (tried to allocate 262144 bytes) in /home/techblim/public_html/wp-content/themes/powermag/inc/lessc.inc.php on line 1576

My website : <http://www.techblimp.com/>

I searched for solution on google and youtube. But those methods are not working for me. I am getting this error on homepage, when I open my website.

Wordpress dashboard and other inside-stuff is working fine. The solutions on YouTube are for the "inside errors".

Did anyone of you have the same problem with their websites? Can you please help?

D3xus - July 14, 2015, 8:17 am

http://codex.wordpress.org/Editing_wp-config.php#Increasing_memory_allocated_to_PHP

Follow the steps in that link to increase memory size.

XuHi - July 17, 2015, 6:30 am

(Jul 13, 2015 02:59 AM)Sahaj Wrote: [\[CITE\]](#) Hi, good morning/afternoon/evening. :)

I recently bought pro hosting from [here](#).

I installed Wordpress today and it was working great. But when I installed a custom theme, I got this error message :

My website : <http://www.techblimp.com/>

I searched for solution on google and youtube. But those methods are not working for me. I am getting this error on homepage, when I open my website.

Wordpress dashboard and other inside-stuff is working fine. The solutions on YouTube are for the "inside errors".

Did anyone of you have the same problem with their websites? Can you please help?

If you have root access on the server do the following:

```
php -i | grep 'Loaded Configuration File'
```

Copy the path shown on screen e.g. /usr/local/lib/php.ini and nano into it or vim depending on OS.

```
nano /usr/local/lib/php.ini
```

```
vim /usr/local/lib/php.ini
```

Locate 'memory_limit' or 'max_allowed_memory' and increase the values.

Save the file and restart Apache (httpd)

```
/etc/init.d/apache restart
```

or

```
/etc/init.d/httpd restart
```

Test your website.... If you don't have root what control panel are you using?