

Forum:[Hack Forums](#)

Thread: [Enable or Disable Battery Life Estimated Time Remaining in Windows 10](#)

Emre_ - September 3, 2019, 6:11 am

This batch script will enable or disable showing the battery life estimated time remaining for the Power icon on the taskbar for all users in Windows 10.

Code :: Enable or Disable Battery Life Estimated Time Remaining in Windows 10

@Echo Off & Cls

net sess>nul 2>&1||(powershell start cmd -ArgumentList """/c %~0"" -verb Runas & exit)

Cls & Mode CON LINES=11 COLS=85 & Color 0E & Title Created By FreeBooter

Echo.

Echo.

Echo.

Echo Do You Want to Show Battery Life Estimated Time Remaining (Y/N)?

Echo.

Echo.

Echo.

Set /p input= RESPONSE:

If /i Not %input%==Y (Goto :_Ex) Else (Goto :_Start)

:_Ex

If /i Not %input%==N (Goto :EOF) Else (Goto :_RegRestore)

:_Start

Reg.exe delete "HKLM\SYSTEM\CurrentControlSet\Control\Power" /v "EnergyEstimationDisabled" /f

Reg.exe delete "HKLM\SYSTEM\CurrentControlSet\Control\Power" /v "UserBatteryDischargeEstimator" /f

Reg.exe add "HKLM\SYSTEM\CurrentControlSet\Control\Power" /v "EnergyEstimationEnabled" /t REG_DWORD /d "1" /f

Cls & Mode CON LINES=11 COLS=65 & Color 0E & Title Created By FreeBooter

Echo.

Echo.

Echo.

```
Echo.  
Echo      Enabling Showing Battery Life Estimated Time Remaining  
Echo.  
Echo.  
Echo.  
Ping -n 6 localhost >Nul  
Exit
```

```
:_RegRestore
```

```
Reg.exe add "HKLM\SYSTEM\CurrentControlSet\Control\Power" /v "EnergyEstimationDisabled" /t  
REG_DWORD /d "1" /f  
Reg.exe add "HKLM\SYSTEM\CurrentControlSet\Control\Power" /v  
"UserBatteryDischargeEstimator" /t REG_DWORD /d "1" /f  
Reg.exe delete "HKLM\SYSTEM\CurrentControlSet\Control\Power" /v "EnergyEstimationEnabled"  
/f
```

```
Cls & Mode CON  LINES=11 COLS=60 & Color 0E & Title Created By FreeBooter
```

```
Echo.  
Echo.  
Echo.  
Echo.  
Echo      Disabling Battery Life Estimated Time Remaining  
Echo.  
Echo.  
Echo.  
Ping -n 6 localhost >Nul  
Exit
```