

Forum:[Hack Forums](#)

Thread: [\[CentOS\] NEED HELP WITH SETTING UP UNREALIRCD \[CentOS\]](#)

i hack rs pk - January 18, 2011, 9:20 am

Hello ive setupped unrealircd but cant get it work so please if some one can please help me i will give you a own channel and a amdin spot in the irc and you can have botnet or whatever you want and its 24/7 uptime :)

So please post here or pm :)

redhot - January 18, 2011, 9:26 am

what error are you getting ?

i hack rs pk - January 18, 2011, 9:29 am

(Jan 18, 2011 10:26 AM)redhot Wrote: [\[CITE\]](#) what error are you getting ?

i have nothing that is named "start" so i dunno how to start it.

redhot - January 18, 2011, 9:31 am

go to the ircd dir and type `./unreal start` without the quotes

i hack rs pk - January 18, 2011, 9:43 am

(Jan 18, 2011 10:31 AM)redhot Wrote: [\[CITE\]](#) go to the ircd dir and type `./unreal start` without the quotes

yeh but it done work

still need help :)

redhot - January 18, 2011, 9:54 am

whats it say when you do that?

firegold - January 18, 2011, 9:56 am

send me a pm, and i will help you to set the thing up---

Violence - January 18, 2011, 10:00 am

When you extract the unreal from the package assuming you did. If you didn't use this command: `tar -xzf whateveryounamedit.tar.gz`

After that's done use this command to access the folder. `cd foldername`

After that you need to config it. If you want everything standard just type: `./Config`

When you do so you shall see this.

Your configuration of unreal ircd has been started. Now you have to press "Enter key" once and then "space bar" until you see following questions.

Quote

Do you want to enable the server anti-spoof protection?

[No] ->

To enable anti-spoof protection option type yes and enter or leave if you want to keep it disabled

then just leave it blank and press enter. According to my suggestion keep it blank.

Quote

What directory are all the server configuration files in?

[/home/username/Unreal3.2] ->

We didn't change the directory so keep it blank and press enter.

Quote

What is the path to the ircd binary including the name of the binary?

[/home/username/Unreal3.2/src/ircd] ->

Again keep it blank and press enter as we didn't changed this path.

Quote

Would you like to compile as a hub or as a leaf?

Type Hub to select hub and Leaf to select leaf.

[Hub] ->

If you are not going to link your ircd with any other irc server then just keep it blank and press enter.

If you want to link your ircd to other irc servers then type leaf and press enter.

Quote

What is the hostname of the server running your IRCd?

[ircd.webshost.net] ->

You don't need to change anything here so just press enter for the next question.

Quote

What should the default permissions for your configuration files be? (Set this to 0 to disable)

It is strongly recommended that you use 0600 to prevent unwanted reading of the file

[0600] ->

Answer has been already given automatically by configuration script so just press enter and go for next question.

Quote

Do you want to support SSL (Secure Sockets Layer) connections?

[No] ->

Many servers does not use this option so my recommendation for you is to leave it blank and go ahead for next question. But if you want to enable this option just type yes and go ahead.

Note: if you are pressing yes you should know what you are doing.

Assuming that you have kept that blank, we are moving to our next question

Quote

Do you want to enable IPv6 support?

[No] ->

If you want to enable this option type yes and go ahead. We are keeping it here disabled.

Quote

Do you want to enable ziplinks support?

[No] ->

You really don't need feature either, so keep it blank.

Quote

Do you want to enable remote includes?

[No] ->

No, its not recommended.

Do you want to enable prefixes for chanadmin and chanowner?

This will give +a the & prefix and ~ for +q (just like +o is @)

Supported by the major clients (mIRC, xchat, epic, eggdrop, Klient, PJIRC, irssi, CGI:IRC, etc.)

Quote

This feature should be enabled/disabled network-wide.

[Yes] ->

Its a cool feature. You might like it to keep it enable. If you have registered the channel, you will be ~yournick instead of @yournick in the channel, and anyone who you have added to the SOP list, or who is +a in the channel, will be &theirnick instead of @theirnick. Type no if you dont want it.

Quote

What listen() backlog value do you wish to use? Some older servers have problems with more than 5, others work fine with many more.

[5] ->

Again keep it blank as we do not need to change this value.

Quote

How far back do you want to keep the nickname history?

[2000] ->

Again keep it blank as we do not need to change this value.

Quote

What is the maximum sendq length you wish to have?

[300] ->

Keep it blank again.

Quote

How many buffer pools would you like?

This number will be multiplied by MAXSENDQLENGTH.

[18] ->

Yes you guessed it right, keep it blank again.

Quote

How many file descriptors (or sockets) can the IRCd use?

[1024] ->

Now this answer depends upon how many users are allowed on your ircd.

Suppose if you have purchased 300 user ircd package then type 300, if you have 1000 user ircd then type 1000.

Quote

Would you like any more parameters to configure?

Write them here:

[]->

If it's standard just hold enter.

After it's done, type: make

It should finish. After that upload you unrealircd.conf file to make your oper and stuff.

Then type: ./unreal start

i hack rs pk - January 18, 2011, 11:07 am

Thanks for all help i appreciate it.

But i never used this way to setup ircd cuz i couldnt get GCC.

And i cant still i hope some one can help me :)

Violence - January 18, 2011, 3:10 pm

(Jan 18, 2011 12:07 PM)i hack rs pk Wrote: [\[CITE\]](#) Thanks for all help i appreciate it.

But i never used this way to setup ircd cuz i couldnt get GCC.

And i cant still i hope some one can help me :)

Use this command then.

yum install gcc

i hack rs pk - January 22, 2011, 11:41 am

i got gcc now but cant do "make" i get error

C?s? ????? - January 22, 2011, 12:08 pm

Hey, pm me i can help you out!!